





Tips and tricks by the APIS Support team

Alexander Weiß, APIS IT GmbH

Selection of contents for the FMEA form

- FMEA Forms Management: Button "New"
- Select only system elements at failure mode level!
- Effects and causes are added automatically via the failure net








AP (Action Priority) is not visible

- No AP catalog available
- Load AP catalog from template (Menu: "Tools | Read template..")
- No AP catalog in template
- Load AP catalog from the file "Example.fme" into the template (Menu: "Tools | Update template..")
- Display of AP disabled
- Enable display of AP (Menu: "View | Display options.."), Structure: "..Additional details", FMEA form: "..Table | Miscellaneous" and "..Table columns"
- Rating is not complete
- Define O, D ratings directly, assign S rating at the effect

New dialog: Read/update template

Only objects with a green arrow (double-click) are loaded or updated. When updating the template, deletions can also be made in the template via a red "x".



Fmea in home office

Software installation:

Local installation of the IQ Software (also NLX Client)
or
remote desktop connection to computer at company workstation

File:

Use local copy of fme file



Optimization of large files

To reduce the file size, you can reorganize the fme file (Menu: "File | Reorganize document"). As *Supervisor* you have additional options.

- Deletion of meeting logs that are no longer required (Menu: "Tools | Forms/Reports | Meeting Log").
- Removing old entries in the Personal Information Manager (PIM).
- Existing document languages that are no longer needed. To delete an unused language, first change to this language and then remove it using the menu "Tools | Delete document language".
- Embedding of unnecessarily large graphic files, which then have a significant share in the total file size. The only remedy for this is to delete the graphic and re-integrate a smaller version of the corresponding graphic file.

Reference language in Terminology and translation

Meaning:

- Main language of the document
- Reference (translation) for all other document languages

In Terminology and translation **always** on the left; this column cannot and **should not** be changed in the exported version (Excel).

Terminology and translation: Detection actions				
Drag a column here to group by this column				
Туре	L	Deutsch	Instan- ces (165)	English
Q		weitere Arbeitsschritte können nicht ausgeführt werden	2	subsequent process steps cannot be performed
Q		Anlötbuchsen werden erst bei vollständig verriegelter Aufnahme freigegeben	1	soldering area on contact pins is accessible only if appliance lock is fully closed
Q		Versuche an Prototypen (B-Muster)	17	tests with prototype
Q		Beschichtungsversuche	2	(test different coatings
Q		🗓 regelmäßige Überprüfung der Druckerfunktionen	1	regular check of correct printer function

Creating your own shortcuts


For maintenance customers, the command finder tool should be visible in the first toolbar:

Example: Creating a "Sort by number" shortcut

- Click on the tool
- Search for "Sort"
- Selection "by Number" in the sorting criteria
- Right click on selection => Context menu appears
- Click on "Add to favorites" in the context menu
- Menu "Help | Select command" shows the new facorites command with Shortcut

When you send screenshots...

...please activate the numbering display



You have got problems?
We can solve them!

support@apis.de